


MS Printhead Dashboard — User Guide


System Overview for General Users



<- Navigation menu is in the top-right corner of every page. Click to switch pages. ->

■ Dashboard — View Printhead Status of All Machines in Real-time

Auto-refreshes every 1 minute



■ MS01 JP4

● Online 8 heads

Col	Row	Serial	Install Date	Color	Duration	Online / Offline Status
1	1	256S-1059	01-Jan-2025	● Cyan	134 days	
1	2	256S-1060	01-Jan-2025	● Magenta	134 days	
2	1	256S-2031	15-Mar-2025	● Yellow	60 days	

Current Serial No. How long in service

■ MS08 JPKevo

✕ Offline


Cannot connect — check network cable

✓ Online: 15 ✕ Offline: 1 ■ Total Heads: 248

<- Summary bar is at the top of the page

History — Review Past Printhead Installation Records by Date

Automatically recorded every 2 hours by the system



■ Search

■ Available Dates

■ Export Excel

MS01 JP4	MS02 JP4	MS03 JP4
✓ Installed (8) 256S-1059 01-Jan-2025 Cyan 256S-1060 01-Jan-2025 Magenta ■ Uninstalled (2) 256S-0900 Removed 15-Dec-2024	✓ Installed (8) 256S-1059 01-Jan-2025 Cyan 256S-1060 01-Jan-2025 Magenta ■ Uninstalled (2) 256S-0900 Removed 15-Dec-2024	✓ Installed (8) 256S-1059 01-Jan-2025 Cyan 256S-1060 01-Jan-2025 Magenta ■ Uninstalled (2) 256S-0900 Removed 15-Dec-2024

<- Each card shows Installed and Uninstalled printheads for that machine on the selected date ->

■ Serial Search — Track the History of Each Printhead by Serial No.

See which machines it was installed on, when, and for how many days in total

1 Enter Serial No.

e.g. "256S-1059" or partial search
e.g. "256S" to find all starting with it

2 Click "Search"

System fetches live data from all machines simultaneously

3 Read the Timeline results

Shows installation history in order from oldest to most recent

Search**256S-1059**

Currently installed · MS05 · 3 machines · 4 times · Total 486 days



MS05 15-Mar-2025 → Present

● Cyan

■ 61 days



MS03 01-Jan-2025 → 14-Mar-2025

● Cyan

■ 72 days



MS01 10-Jul-2024 → 31-Dec-2024

● Cyan

■ 174 days



MS01 01-Jan-2024 → 09-Jul-2024


● Cyan

■ 190 days

<- Green bar on left = currently installed | Dot on timeline = period of use ->

■ All Serials — View Every Serial No. in the System at Once

View the complete printhead inventory — filter and sort as needed



■ Search Serial / Color...

Installed from

to

■ Export

● Installed: 180

■ Uninstalled: 64

Total: 244 | Showing: 180

#	Serial No.	Status	■ Machine	Col/Row	Color	Int■Type	Install Date	Removed Date
1	256S-1059	● Installed	MS05	Col.1 Row.1	● Cyan	Water	01-Jan-2025	Active
2	256S-1060	● Installed	MS05	Col.1 Row.2	● Magenta	Water	01-Jan-2025	Active
3	256S-2031	● Installed	MS03	Col.2 Row.1	● Yellow	Solvent	15-Mar-2025	Active
4	256S-0900	■ Uninstalled	MS01,MS03	—	● Cyan	Water	10-Jul-2024	31-Dec-2024

<- Click column header to sort | Click any row to open that Serial Timeline ->